

# 6. Network ????

- [Dell N1548 snmp](#)
- [Dell N1548 Enable/Disable](#)
- [n1548 mgmt ip](#)
- [n1548](#)
- [N1548](#)
- [N1548](#)
- [N1548 \(admin\)](#)
-

# Dell N1548 snmp??

n1548 [ ] [ ] [ ] [ ] snmp [ ]

snmp [ ] [ ] [ ] [ ] eng [ ] [ ] , snmp [ ] [ ] 192.168.100.10 [ ] [ ] [ ] [ ]

```
console>enable
console#configure
Console(config)#hostname master-sw
Console(config)#snmp-server community eng ro
console(config)#snmp-server host 192.168.100.10 eng
console(config)#snmp-server enable traps link
```

# Dell N1548? ??? Enable/Disable

1. 37   shutdown

```
#configure
(config)#interface gigabitethernet 1/0/37
(config-if-Gil/0/37)#shutdown
```

2. 37

```
#configure
(config)#interface gigabitethernet 1/0/37
(config-if-Gil/0/37)#no shutdown
```

# n1548 mgmt ip ??

console[ ] [ ] mgmt ip[ ] / config save

```
Console(config)#enable
Console(config)#configure
Console(config)#interface vlan 1
Console(config-if)#ip address 192.168.200.10 255.255.255.0
Console(config-if)#exit
Console(config-if)#ip routing
Console(config)#ip default-gateway 192.168.200.1
console(config)#exit
```

```
console#copy running-config startup-config
```

This operation may take few minutes.

Management interfaces will not be available during this time.

Are you sure you want to save? (y/n) y

Configuration Saved!

# n1548 ?????

config[ ] [ ]

```
test-sw(config)#banner motd "-----
```

```
test
```

```
-----"
```

# N1548 ?? ?? ??

N1548 2 port description

```
test-sw(config-if-Gi1/0/1)#interface gigabitethernet 1/0/2
test-sw(config-if-Gi1/0/1)#description 192.168.50.123
test-sw(config-if-Gi1/0/1)#show interfaces configuration
```

# N1548 ?????? ??????

N1548 [ ] [ ] [ ] [ ] [ ] [ ] [ ] [ ]

[ ] [ ] [ ] [ ] [ ] testsw [ ] [ ]

```
console>enable
console#configure
Console(config)#hostname testsw
```

# N1548?? ???? (admin)

1. 配置 (配置 admin / 配置 adminpass 配置)

```
test_sw(config)#username admin password adminpass privilege 15

test_sw(config)#aaa authentication login default local

test_sw(config)#aaa authentication login default line

test_sw(config)#aaa authentication enable default line

Q07-L2-1(config)#enable password adminpass
```

2. 配置 配置 配置 配置

```
test_sw(config)#line console

test_sw(config-line)#login authentication default

test_sw(config-line)#enable authentication default

test_sw(config-line)#password adminpass

test_sw(config-line)#exit
```

3. telnet 配置 配置 配置

```
test_sw(config)#line telnet

test_sw(config-telnet)#login authentication default

test_sw(config-telnet)#enable authentication default

test_sw(config-telnet)#password adminpass
```

```
test_sw(config-telnet)#exit
```

???

?? (???)

### 1. Dell N1548

```
dell_sw#copy running-config startup-config
```

This operation may take few minutes.

Management interfaces will not be available during this time.

Are you sure you want to save? (y/n) y

Configuration Saved!

### 2. Cisco

```
Switch#copy running-config startup-config
```

Destination filename [startup-config]?

Building configuration...

[OK]